# IDA Teams: Ic command reference manual

## **Table of Contents**

1. Introduction.	
2. Command-line options	1
3. Commands	3
3.1. Operating with metadata	3
3.1.1. hist show	3
3.1.2. hist pushes	
3.1.3. hist del	8
3.2. Various information	12
3.2.1. info	12
3.2.2. users	12
3.2.3. stats	12
3.3. Administrative commands	14
3.3.1. Managing users	14
3.3.2. Managing sessions	14
3.3.2.1. session list	14
3.3.2.2. session kill	14
4. Concepts	15
4.1. What is the Lumina server	15
4.1.1. Lumina server vs Hex-Rays Vault server: what is the difference?	15
4.1.2. Functions metadata	
4.1.3. Metadata contents	15
4.1.4. Pushing & overriding metadata	15
4.1.5. Metadata history	
4.1.6. File contents	
Appendix A: Commands	16
A.1. String patterns	
A.2. Timerange formats	
A.3. Speed of retrieving changes	16

Last updated on October 16, 2023 - v8.3

# 1. Introduction

The Ic executable provides a command-line interface to interact with a Lumina server and its contents.

NOTE

virtually all the commands described in this document, require administrator rights; "regular" users will typically not have the necessary privileges.

# 2. Command-line options

## -h, --host HOSTNAME[:PORT]

Lumina host name and port (if port is omitted, it defaults to 443)

## -u USERNAME

specify username

## -p PASSWORD

specify password

## -v, --verbose

verbose output

In order to connect to a Lumina server, Ic must at least be provided with a hostname and a valid user-password pair.

TIP

In order to keep the various commands' syntax as clear as possible, we will omit the login options from commands for the rest of this manual.

Other options exists, specific to each lc command (see Commands).

## 3. Commands

The following commands are accepted by Ic:

## 3.1. Operating with metadata

Commands in this section let users view metadata stored in the Lumina server and their history.

## 3.1.1. hist show

#### hist show [OPTION]

Queries history of changes for function(s).

The following informations will be displayed for each change:

- · The ID of the change
- · The timestamp of the change
- The ID of the push that contains the change
- The name of the function at that change (+ (\*) if it has been modified past this change)
- · optional: The username of the user that pushed this change
- · optional: The name of the license associated with the push for this change
- · optional: The email of the license associated with the push for this change
- · optional: The ID of the license associated with the push for this change
- · optional: The ID of the function
- optional: The effective address (EA) of the function in the input file for the change
- · optional: The hash of the function
- $\boldsymbol{\cdot}$  optional: The path of the idb file where the change came from
- · optional: The hash of the file where the change came from
- · optional: The path of the file where the change came from

**TIP** Wildcards can be used to facilitate the usage of options that take strings as input. See the appendix.

#### Options

#### -a, --additional-fields LIST

Comma-delimited list of additional info to display (username, license\_name, license\_email, license\_id, func\_id, func ea, calcrel hash, idb path, input hash, input path, all)

#### -d, --details

Show details (diff-like) for each change

#### --chronological

Display entries in chronological order (defaults to reverse-chronological).

#### -m, --max-entries NUMBER

maximum number of entries to fetch (defaults to 100)

#### -I, --license-id LICENSE

license ID (XX-XXXX-XXXX-XX format) to operate on

## -r, --history-id-range RANGE

history ID range(s) to operate on (start0..end0 [...])

## -t, --time-range RANGE

time range to operate on (start..end) see the appendix

#### -i, --idb IDB

IDB name(s) to operate on

#### -f, --input FILE

input file(s) to operate on

#### -u, --username USERNAME

username(s) to operate on

#### -n, --func NAME

function name(s) to operate on

#### -h, --input-hash HASH

input file hash(es) to operate on

#### -p, --pushes-id-range RANGE

Pushes ID range(s) to operate on (start0..end0 [...])

## -c, --calcrel-hash HASH

function hash(es) to operate on

#### --last-change

Select only the last change for a function (which speeds up execution)

#### Examples:

List the last 8 changes ("-m 8" specifies the number of changes to show; the default order is reverse-chronological)

List changes from id 9 up to (but excluding) id 14

List changes using multiple ranges (9..14,505..515; in this case, there were no changes after 507 in the database)

Find changes from a specific idb file ("-i"), showing the function hash and ea ("-a" adds additional columns to the output)

Show the first 4 changes ("-m4") with their input file(s) (in "--chronological" order; "-a" adds an additional column)

Show the last change by a user ("-u" indicates the user, "-m1" means show 1 change only, "-a" adds an additional column)

```
alice@alice_PC$ lc hist show -ubob -m1 -a username
Change Time
Push Func name Username
-----
502 2022-09-15 14:48:15 2 fstat bob
# Shown 1 results (more are available...)
```

Show up to 4 changes ("-m4") between two dates ("-t" indicates a range of "YYYY-MM-DD" dates)

Show up to 4 changes ("-m4") between two "now"-relative dates ("-t", from 2 weeks ago to 5 minutes ago) ("-a" adds an additional column)

Show up to 4 changes ("-m4") between two "now"-relative dates ("-t", from 2 weeks ago to 5 minutes ago) ("-a" adds an additional column), only select the last change for each function

```
# Shown 4 results (more are available...)
```

Show up to 4 changes ("-m4"), occurring after a "now"-relative date ("-t", from 6 hours ago up to now)

Show changes about a specific function name ("-n")

Show changes about a function name ("-n") searched by wildcard ("like:...")

Show metadata details ("--details") in changes for a function ("-n"); this particular change added a new function

```
alice@alice_PC$ lc hist show -n is_location_form --details
   Change Time Push Func name
   >> Score
        >> - 0
              + 1445
        >>
        >> Name
              - None
        >>
        >>
              + is_location_form
        >> Prototype
        >>
              + 0C303D08626F6F6C65616E0207
        >>
        >> Member @ 0x8
        >>
             .type
                 - None
        >>
        >>
                 + 07
        >>
              .cmt
               - None
        >>
        >>
        >>
              .rptcmt
        >>
               - None
                 +
        >>
        >> Insn operands @ 0+0x3
        >>
              - [<no ops repr>]
              + [op0=0xb, op1=0x0, op2=0x0, op3=0x0, op4=0x0, op5=0x0, op6=0x0, op7=0x0]
        >> Insn operands @ 0+0x9
              - [<no ops repr>]
        >>
              + [op0=0xb, op1=0x0, op2=0x0, op3=0x0, op4=0x0, op5=0x0, op6=0x0, op7=0x0]
        >>
        >> Insn operands @ 0+0xf
              - [<no ops repr>]
               + [op0=0xb, op1=0x0, op2=0x0, op3=0x0, op4=0x0, op5=0x0, op6=0x0, op7=0x0]
```

```
>> Insn operands @ 0+0x15
             - [<no ops repr>]
             + [op0=0xb, op1=0x0, op2=0x0, op3=0x0, op4=0x0, op5=0x0, op6=0x0, op7=0x0]
      >> Insn operands @ 0+0x1b
      >>
             - [<no ops repr>]
             + \ [ op0=0xb, \ op1=0x0, \ op2=0x0, \ op3=0x0, \ op4=0x0, \ op5=0x0, \ op6=0x0, \ op7=0x0 ]
      >>
      >> Insn operands @ 0+0x21
             - [<no ops repr>]
             + [op0=0xb, op1=0x0, op2=0x0, op3=0x0, op4=0x0, op5=0x0, op6=0x0, op7=0x0]
      >> Insn operands @ 0+0x27
      >>
             - [<no ops repr>]
             + [op0=0xb, op1=0x0, op2=0x0, op3=0x0, op4=0x0, op5=0x0, op6=0x0, op7=0x0]
      >>
# Shown 1 results
```

## 3.1.2. hist pushes

## hist pushes [OPTION]

Shows pushes to the Lumina server.

Options

#### -a, --additional-fields LIST

Comma-delimited list of additional info to display (license\_name, license\_email, license\_id, all)

## -t, --time-range TIMESTAMP

timestamp

#### -u. --username USERNAME

username(s) to operate on

#### -I, --license-id LICENSE

license ID (XX-XXXX-XXX format) to operate on

## -m, --max-entries NUMBER

maximum number of entries to operate on (defaults to 100)

#### --chronological

Display entries in chronological order (defaults to reverse-chronological).

## Examples:

## List all pushes from a specific license ID

List all pushes from licenses with IDs matching a pattern ("-a" adds an additional column)

```
alice@alice_PC$ lc hist pushes -l like:AA-% -a license_id

Push ID Time

User name License ID

DB path

2022-09-15 14:48:18 alice

AA-A11C-AC8E-01 /home/alice/work/pc_math_b_64.elf.i64

2022-09-15 14:48:17 alice

AA-A11C-AC8E-01 /home/alice/work/pc_dwarf_arrays.elf.idb

# Shown 3 results
```

#### Show the first push

```
alice@alice_PC$ lc hist pushes --chronological -m 1
Push ID Time User name IDB path
1 2022-09-15 14:47:44 alice /home/alice/work/pc_dwarf_arrays.elf.idb
# Shown 1 results (more are available...)
```

#### List all pushes between two timestamps

## List all pushes from two users ("-a" adds an additional column)

## 3.1.3. hist del

## hist del [OPTION]

Deletes history and metadata for functions.

#### Options

## -s, --silent

Do not ask for confirmation before deleting history

## -I, --license-id LICENSE

license ID (XX-XXXX-XXX format) to operate on

### -r, --history-id-range RANGE

history ID range(s) to operate on (start0..end0 [...])

#### -t, --time-range RANGE

time range to operate on (start..end) see the appendix

### -i, --idb IDB

IDB name(s) to operate on

#### -f, --input FILE

input file(s) to operate on

#### -u, --username USERNAME

username(s) to operate on

#### -n, --func NAME

function name(s) to operate on

### -h, --input-hash HASH

input file hash(es) to operate on

### -p, --pushes-id-range RANGE

Pushes ID range(s) to operate on (start0..end0 [...])

#### -c, --calcrel-hash HASH

function hash(es) to operate on

#### --last-change

Select only the last change for a function (which speeds up execution)

#### Examples:

Display the last 10 changes, with their input file(s) and function ID(s)

Change	Time		Push	Func name	Func ID	Input path
507	2022-09-15	14:48:18	5	math_things	506	/home/alice/work/pc_math_b_64.elf
506	2022-09-15	14:48:17	4	calc_things (*)	506	/home/alice/work/pc_math_a_64.elf
505	2022-09-15	14:48:17	4	start	505	/home/alice/work/pc_math_a_64.elf
504	2022-09-15	14:48:16	3	keygen_window_dialog_proc_a	504	<pre>C:\malware\apts\pc_keygenme_3.pe</pre>
503	2022-09-15	14:48:16	3	display_keygen_window	503	<pre>C:\malware\apts\pc_keygenme_3.pe</pre>
502	2022-09-15	14:48:15	2	fstat	502	/Users/bob/idbs/pc_dwarfdump.elf
501	2022-09-15	14:48:15	2	umoddi3	501	/Users/bob/idbs/pc_dwarfdump.elf
500	2022-09-15	14:48:15	2	udivdi3	500	/Users/bob/idbs/pc_dwarfdump.elf
499	2022-09-15	14:48:14	2	dwarf_get_ADDR_name	499	/Users/bob/idbs/pc_dwarfdump.elf
498	2022-09-15	14:48:14	2	dwarf_get_FRAME_name	498	/Users/bob/idbs/pc_dwarfdump.elf

## Delete all changes for functions matching a pattern

```
alice@alice_PC$ lc hist del -s -n like:%dwarf%
   267 entries deleted from history
alice@alice_PC$ hist show -m10 -a input_path,func_id
   Change Time Push Func name
                                                           Func ID Input path
                                math_things
calc_things (*)
         2022-09-15 14:48:18 5 math_things
   507
                                                            506
                                                                   /home/alice/work/pc_math_b_64.elf
         2022-09-15 14:48:17 4
2022-09-15 14:48:17 4
   506
                                                            506
                                                                   /home/alice/work/pc_math_a_64.elf
   505
                                 start
                                                            505
                                                                    /home/alice/work/pc_math_a_64.elf
          2022-09-15 14:48:16 3
   504
                                 keygen_window_dialog_proc_a 504
                                                                   C:\malware\apts\pc_keygenme_3.pe
   503 2022-09-15 14:48:16 3 display_keygen_window 503
                                                                   C:\malware\apts\pc_keygenme_3.pe
   502
         2022-09-15 14:48:15 2 fstat
                                                            502
                                                                   /Users/bob/idbs/pc_dwarfdump.elf
   501
          2022-09-15 14:48:15 2 __umoddi3
                                                            501
                                                                   /Users/bob/idbs/pc_dwarfdump.elf
   500
         2022-09-15 14:48:15 2
                                 __udivdi3
                                                            500
                                                                   /Users/bob/idbs/pc_dwarfdump.elf
                                                            474
   474
          2022-09-15 14:48:14 2 free_macro_stack
                                                                   /Users/bob/idbs/pc_dwarfdump.elf
          2022-09-15 14:48:14 2
                                 print_line_detail
                                                            468
                                                                   /Users/bob/idbs/pc_dwarfdump.elf
   # Shown 10 results (more are available...)
```

#### Delete all changes stemming from a specific file

```
alice@alice_PC$ lc hist del -s -f/Users/bob/idbs/pc_dwarfdump.elf
```

```
228 entries deleted from history
```

## List the changes from pushes 1 to 5 (not included), showing their input file(s)

```
alice@alice_PC$ lc show -p1..5 -a input_path
  Change Time Push Func name
                                                Input path
  _____
  506 2022-09-15 14:48:17 4 math_things
                                               /home/alice/work/pc_math_a_64.elf
  505 2022-09-15 14:48:17 4 start
                                               /home/alice/work/pc_math_a_64.elf
  504 2022-09-15 14:48:16 3 keygen_window_dialog_proc_a C:\malware\apts\pc_keygenme_3.pe
  /home/alice/work/pc_dwarf_arrays.elf
                                               /home/alice/work/pc_dwarf_arrays.elf
        2022-09-15 14:47:44 1
  5
                                                /home/alice/work/pc_dwarf_arrays.elf
                          main
        2022-09-15 14:47:44 1
                                                /home/alice/work/pc_dwarf_arrays.elf
                          frame_dummy
                          __do_global_dtors_aux
  3
        2022-09-15 14:47:44 1
                                                /home/alice/work/pc_dwarf_arrays.elf
        2022-09-15 14:47:44 1
                           _start
                                                /home/alice/work/pc_dwarf_arrays.elf
        2022-09-15 14:47:44 1
                                                /home/alice/work/pc_dwarf_arrays.elf
                          .init_proc
  # Shown 11 results
```

#### Delete one single change

```
alice@alice_PC$ lc hist del -s -r505..506
1 entries deleted from history
```

## Delete all the changes from push 1

## Delete all changes by a user

```
alice@alice_PC$ lc hist del -s -udamian
2 entries deleted from history

alice@alice_PC$ hist show -a func_id
Change Time Push Func name Func ID
-----
507 2022-09-15 14:48:18 5 math_things 506
506 2022-09-15 14:48:17 4 calc_things (*) 506
# Shown 2 results
```

## Delete the last change for a function

```
alice@alice_PC$ lc hist del -s --func math_things --last-change
1 entries deleted from history

alice@alice_PC$ hist show -a func_id
Change Time Push Func name Func ID
------506 2022-09-15 14:48:17 4 calc_things 506
# Shown 1 results
```

#### Delete all remaining changes for a function by name

```
alice@alice_PC$ lc hist del -s --func calc_things
```

1 entries deleted from history

alice@alice\_PC\$ hist show
 # Shown 0 results

## 3.2. Various information

## 3.2.1. info

#### info

Shows lumina connection information.

#### Example:

```
alice@alice_PC$ lc info
Hex-Rays Lumina Server v8.0
Lumina time: 2022-08-29 10:13:37, up since 2022-08-21 21:00:05
MAC address: FF:32:67:FF:D3:00
Client name: alice *ADMIN*
Client host: 127.0.0.1
```

## 3.2.2. users

#### users

Shows users.

## Example:

## 3.2.3. stats

## stats [OPTION]

Shows the numbers of functions, pushes, history records, IDBs and input files stored in the Lumina server database.

## Options

#### -u, --username USERNAME

username(s) to operate on

## Examples:

```
alice@alice_PC$ lc stats
Consolidated statistics from lumina_server:
Number of functions: 4
Number of pushes: 5
Number of history records: 6
Number of IDBs: 3
Number of input files: 3
```

## Retrieve the statistics for a list of users

```
alice@alice_PC$ lc stats -ualice,bob,russ
```

## 3.3. Administrative commands

These commands require that the user executing them has admin privileges.

## 3.3.1. Managing users

Users management is delegated to the Hex-Rays Vault server; the administrator will be in charge of performing the adding/editing/deleting of users on the Hex-Rays Vault server itself.

Whenever a user connects to the Lumina server, it will turn to the Hex-Rays Vault server to ask it to perform authentication.

A "shadow" of the user data is nonetheless kept in the Lumina server's database, in order to be able to attribute contributions.

The host name (and port) of the Hex-Rays Vault server need to be present in the lumina.conf file.

## 3.3.2. Managing sessions

## 3.3.2.1. session list

#### session list

Lists the current connections to the Lumina server. For each connection, the currently executed query (if any) is shown.

## Example:

```
alice@alice_PC$ lc session list id=1642 peer="127.0.0.1", user="...", license="...", e-mail="...", established="2022-08-16 17:13:21" current_query="INSERT INTO pushes (fk_idb, fk_user) VALUES (?, ?)" (0msec)
```

## 3.3.2.2. session kill

#### session kill ID

Kills an existing connection to the Lumina server.

#### **Parameters**

ID The connection to kill, as shown by the session list command

## Example:

```
alice@alice_PC$ lc session list
id=1 peer="127.0.0.1", user="...", license="...", e-mail="...", established="2022-09-20 16:47:07" current_query=""
(0msec)
alice@alice_PC$ lc session kill 1
Connection killed
alice@alice_PC$ lc session list
No connections.
```

# 4. Concepts

## 4.1. What is the Lumina server

The Lumina server is a "functions metadata" repository.

It is a place where IDA users can **push**, and **pull** such metadata, to ease their reverse-engineering work: metadata can be extracted from existing projects, and re-applied effortlessly to new projects, thereby reducing (sometimes dramatically) the amount of time needed to analyze binaries.

## 4.1.1. Lumina server vs Hex-Rays Vault server: what is the difference?

While the workflow with the Hex-Rays Vault server and associated tools (hv, hvui and IDA's diff/merge modes) are extremely powerful for working on multiple revisions of the same binaries, the Lumina server in turn eases the replication of past efforts to new projects.

In effect, the Lumina server offers another "dimension" to collaborative reverse-engineering efforts.

## 4.1.2. Functions metadata

The Lumina server associates "function metadata" to functions, by means of a (md5) hash of those functions: whenever it wants to push information to, or pull information from the server, IDA will first have to compute hashes of the functions it wants to retrieve metadata for, and send those hashes to the Lumina server.

Similarly, when IDA **push**es information to the Lumina server, it will first compute hashes for the corresponding functions, extract the metadata corresponding to those from the .idb file, and send those hash+metadata pairs to the server.

## 4.1.3. Metadata contents

Metadata about functions can include:

- · function name
- function address
- · function size
- function prototype
- function [repeatable] comments
- instruction-specific [repeatable] comments
- anterior/posterior (i.e., "extra") comments
- · user-defined "stack points" in the function's frame
- · the function frame description and stack variables
- · instructions operands representations

## 4.1.4. Pushing & overriding metadata

When a user pushes metadata about a function whose md5 hash isn't present in the database, the Lumina server will simply create a new record for it.

However, when a user pushes metadata about a function whose md5 hash (and associated metadata) is already present in the database, the Lumina server will attempt to "score" the quality of the old metadata and the quality of the new metadata. If the score of the new metadata is higher, the new function metadata will override the previous one.

NOTE

When a user asks IDA to push *all* functions to the Lumina server, IDA will automatically skip some functions: those that still have a "dummy" name (e.g., sub\_XXXX), or that are below a certain size threshold (i.e., 32 bytes) will be ignored.

## 4.1.5. Metadata history

The Lumina server retains a history of the metadata associated to functions. Using the lc utility, it is possible to dig into

that history, and view changes (detailed diffs, too.)

## 4.1.6. File contents

It's worth pointing out that when pushing metadata to the Lumina server, IDA will not push the binary file itself. Only the following metadata about the file itself will be sent:

- · the name of the input file
- · the name of the IDB file
- a md5 hash of the input file

The Lumina server cannot therefore be used as a backup/repository for binary files & IDBs (that would be the role of the Hex-Rays Vault server)

# Appendix A: Commands

## A.1. String patterns

Options that take strings as inputs can be enhanced through wildcards. The following wildcards are available:

represents zero, one or multiple characters.

represents one character.

To use wildcards in a string, it must be prefixed with like: e.g. -n like: %main%.

## A.2. Timerange formats

For timeranges, the following syntaxes are supported:

- <ts>...<ts> (from timestamp to (but not including) timestamp)
- <ts> (only one timestamp)

Where <ts> can be of the form:

- yyyy-mm-dd HH:MM:SS: e.g., 2022-09-12 11:38:22
- yyyy-mm-dd: e.g., 2020-03-12
- +|-<count><unit>: this is a "now-relative" timestamp, where <unit> must be one of w, d, H, M, S for weeks, days, hours, minutes or seconds respectively. E.g., -4d, +5w, -8H, +1H, ...

NOTE

when using the <ts> syntax (i.e., only 1 timestamp is provided, not an actual range), the final range will be either "from now to <ts>", or "from <ts> to now", depending on whether <ts> is before, or after, the present time.

# A.3. Speed of retrieving changes

Although it may seem like a simple operation, lc hist show is actually a very demanding one: by default it will have to fetch bits of information from multiple tables (e.g., in order to provide information about which change was superseded by a later one.)

This can be significantly sped up through the use of --last-change: this option lets the server issue a much simpler query, resulting in significantly reduced processing time.